

2013

Image Slider Installation

Installation set for TechPerspect's Image Slider App

This document contains the installation listing of image slider app



Contents

Installation.....	2
Step 1: Add App.....	2
Step 2: Images Management.....	4
Step 3: Configure App.....	7
Effects.....	9
Interval.....	9
Library Name	9
Custom Picture Library	10
Image Count	12
Navigation Icons	12
Visibility	12
Behaviour.....	12
Style	13
Image Dimensions	13
Sorting	14
Public Website.....	15
Limitation.....	15
consult@techperspect.com	16

Installation

Step 1: Add App

- a) Once you have added Image Slider App to your site, create new wiki page or add new web part and then add image slider app to your page.





Image Slider Installation

b) After saving your page you will see the screen below.



Step 2: Images Management

- a) Navigate to Site Contents and click on Image Slider App.




Image Slider Installation

- b) Once clicked on Image Slider App you will see the Slider Library in the page.






Image Slider Installation

- c) Add items to library that images will display in the slider. You can add further optional details like Title, Description, and Sequence.



Step 3: Configure App

- a) Now open the page you created and go to edit web part properties.



- b) Expand the node named "Slider App" in web part Properties





Image Slider Installation

Effects

Effects reflect the transition effect of the images in the image slider app. By default “Block” is selected.



Interval

Here in the textbox you can enter the time interval (in milliseconds) between the images in the Slider App.



Library Name

In the Slider App the default library being used to display images is the Slider Library. Instead of Slider Library one can use their own library but that library must be a picture library and read permission has to be given to Image Slider App for the custom library selected.



Image Slider Installation

Custom Picture Library

- i. Navigate to site contents and hover on the Image Slider App Part. Click on the “. . .” and then go to Permissions as shown below





Image Slider Installation

- ii. After that you will see the app asking for the read permission for the different picture libraries listed in the dropdown. Select your custom picture library from the drop down from which you want to show the images into slider and then click on "here" to trust.



- iii. Then go to app part properties again and enter your custom picture library name in place of Slider Library and click ok to take effect.





Image Slider Installation

Image Count

This property specifies the number of images to show in the Image Slider App.



A screenshot of a configuration field labeled "Images Count". It consists of a text input box with the number "5" entered inside, and a small square button to the right of the input box containing the number "5".

Navigation Icons


Visibility

This property specifies that to show or hide the navigation icon in Slider App.



A screenshot of a configuration field labeled "Navigation Icon Visibility". It features a dropdown menu with two options: "Show" (highlighted in blue) and "Hide".

Behaviour



A screenshot of a configuration field labeled "Navigation Icon: Behaviour". It contains a text description: "Navigation Icon: 'Inside Slider' shows navigation images inside the slider image and 'Outside Slider' shows navigation images outside the slider image". Below the text is a dropdown menu with two options: "Inside Slider" (highlighted in blue) and "Outside Slider".

Image Slider Installation

Style

You can select the navigation type of the sliding images. By default the Dots option is selected.




Image Dimensions

You can adjust slider height and width according to your image size. For best viewing keep the image and slider dimension same. By default slider dimensions are height 250px and width 500px.

A screenshot of a form with two input fields. The first field is labeled 'Image Height' and contains the value '250'. The second field is labeled 'Image Width' and contains the value '500'. There is a horizontal dotted line between the two fields.

Image Slider Installation

Sorting

You can sort the images by a particular column in the picture library. By default images are sorted by Modified column. You can replace that with predefined as well as custom column and sort images by it.



Public Website

You can use this app on public websites only if you have your own farm premises and provide access to anonymous users and after that by using following PowerShell commands

```
$web = Get-SPWebApplication -Identity http://your web address
```

```
$web.ClientCallableSettings.AnonymousRestrictedTypes.Remove( [Microsoft.SharePoint.SPList], "GetItems")
```

```
$web.Update()
```

Limitation

This app doesn't work for the online 365 public site for anonymous users as Microsoft doesn't provide ***\$web.ClientCallableSettings.AnonymousRestrictedTypes*** to execute on shared environment.



consult@techperspect.com

TechPerspect is a business technology service & solution provider helping organizations realize the true potential of technology. TechPerspect was started by a diverse team of professionals who came from different backgrounds and had already scripted successful careers for themselves. Their vision is to build an organization that is among the most admired companies globally for its value services and that is reflected in the way we do business. Providing innovative technology solutions to different businesses we intend to be called by our clients

“A technology firm with a difference”

We provide Innovative technology solutions to resolve business problems and thus help achieving organizational efficiency & effectiveness.

www.techperspect.com

